

Automation Anywhere 安装简易说明

1. 安装前提条件(Control Room)

a) 权限

- 要运行 Automation Anywhere Enterprise 控制室安装程序，用户需要系统管理员角色。
- 要安装和管理（运行/启动、重启、停止）Automation Anywhere Enterprise 控制室 Windows 服务，应向配置为使用 Enterprise 控制室的服务/域账户用户授予管理员和作为服务登录权限。

b) 软件要求

软件	最低要求
操作系统	Windows Server 2012 R2
.NET Framework	Microsoft .NET 4.6
数据库管理系统	Microsoft SQL Server 2014 SP1（快速安装）、 Microsoft SQL Server 2012（自定义安装） 11.3.1 或
	<ul style="list-style-type: none">• 11.3.1 Oracle Database 12.1.0.2
Web 浏览器	<ul style="list-style-type: none">• Chrome 57 版及更高版本• Internet Explorer 10 和 11 版• Firefox 52 版及更高版本

注：单独安装以下软件（如果以前未安装）：

- Microsoft .NET Framework 4.6
- Microsoft SQL Server 2014 SP1（仅适用于快速安装）
- **11.3.1** Oracle Database 12.1.0.2（仅适用于自定义安装）

c) 硬件要求

硬件	最低要求
处理器	8 核英特尔至强处理器
RAM	16 GB
磁盘空间	500 GB

2. 安装前提条件(Client)

(支持 32 位和 64 位操作系统版本)


操作系统	版本
Microsoft Windows Server 2016	Datacenter/Standard Edition
Microsoft Windows 10	Pro/Enterprise Edition
Microsoft Windows Server 2012 R2	Standard Edition
Microsoft Windows Server 2012	Standard Edition
Microsoft Windows Server 2008 R2	Standard Edition
Microsoft Windows 8.1/8	Pro/Enterprise Edition
Microsoft Windows 7 SP1	Professional Edition

处理器： 推荐 - 3.5 MHZ + 4 核及以上，8 GB RAM 或更高；4 个虚拟 CPU (vCPU) 或逻辑处理器，每个 vCPU 各 1.2 到 1.5 GHz 速度，每台虚拟机各 6-8 GB RAM。

硬盘： 300 MB 可用硬盘空间用于安装。


3. 安装包说明

解压缩后可以看到以下压缩包，各自再进行解压缩。




AAE_MSSQL_Express_2014SP1.exe 是微软数据库安装包。

Automation Anywhere Enterprise_11.3.2.exe 是控制中心(Control Room)的安装包。




AAE_Client_AND_Remote_Agent_11.3.2.zip 解压缩后文件夹结构如下。




1.Base Release 11.3.2 是基础安装包， 2.Service_Release 包含补丁。注意， Control Room 的版本不能低于客户端版本。版本 11 和 10 不能通用。

4. 安装 SQL Server Express


a) 选择 New SQL Server Stand-alone installation




b) 点击下一步




c) 点击下一步



d) 默认设置，省略后续步骤，均点击下一步(Next)按钮即可。



e) 安装完毕




5. 配置 SQL Server Express


通常在菜单里能够找到Sql Server Configuration Manager。
如果找不到可以在以下路径(64 位 Win10Pro 为例)找到：
C:\Windows\SysWOW64\SQLServerManager12.msc

a) 配置 SQL Server Express,


1) 保证 TCP/IP 协议打开




2) 配置 SQL Server 网络



3) 配置 port




4) 重启 SQL Server Express




6. 安装 AAE Control Room


a) 双击安装文件




b) 点击 install




c) 点击 install



d) 点击 Next



e) 选择 express




f) 点击 Next (如有以下错误信息, 请检查 SQL Server Tcp/ip 设置)


The screenshot shows the 'Database Server' configuration window in the 'Automation Anywhere Enterprise - 11.1.0 - InstallShield Wizard'. The window title is 'Automation Anywhere Enterprise - 11.1.0 - InstallShield Wizard'. The main heading is 'Database Server' with the subtitle 'Select database server and authentication method'. The window contains the following fields and options:

- Database server:** A dropdown menu showing '(local)\SQLEXPRESS' and a 'Browse...' button.
- Database Port:** A text box containing '1433'.
- Use Secure Connection
- Certificate (Optional):** A text box and a 'Browse...' button.
- Windows authentication and Sql Server authentication
- Login ID:** A text box.
- Password:** A text box.
- Name of Control Room database:** A text box containing 'CRDB-NEW'.
- Name of Bot Insight database:** A text box containing 'BotInsight'.

At the bottom of the window, there are three buttons: '< Back', 'Next >', and 'Cancel'.




g) 点击 finish。



7. 确认安装内容

a) 点击桌面 control room 图标以打开控制中心，按照提示设置相应信息。



b) 选择 Express mode

Automation ANYWHERE Enterprise Control Room

Welcome! Let's get started Save and log in

CONTROL ROOM FIRST...

Username
Admin

First name
Manny

Last name
Manager

Email
manager.your.co@gmail.com

SECURITY QUESTIONS

Question 1
Pet?
Answer: *****

Question 2
Sport?
Answer: *****

Question 3
Singer?
Answer: *****

CREDENTIAL SETTINGS

Credentials settings

The Credential Vault master key allows you to connect to the Credential Vault where you can create and store credentials that are required when running bots.

IMPORTANT NOTE: Save the master key, now, in a safe place for future reference. If you need it in the future, and you do not have it, you may not be able to access the Control Room.

Credentials Vault master key

Select the connection mode for the Credential Vault.

Express mode
Save your master key and automatically connect to the Credential Vault every time the Control Room restarts.

Manual mode
Every time the Control Room restarts, manually enter the master key to connect to the Credential Vault.
More secure and recommended for use in a production environment.

Master key

PfJTQUtleVZhbHVPjxNb2R1bHVzPkFLRIB6RHVBcUtDUW5pcnlwNmhhQVdHV1FUUTVzQnI5Nkh4eGlyYXpYdldwTVRET2c Copy

< Back

c) 创建用户

Automation ANYWHERE Enterprise Control Room

Dashboards >

Home Dashbo

Home Us

DASHBOARDS

- Home
- Bots
- Devices
- Audit
- Workload
- Insights

ACTIVITY

Acti

BOTS

Bot Veloc

DEVICES

WORKLOAD

AUDIT LOG


ADMINISTRATION

- Settings
- Users
- Roles
- Licenses
- Migration

Y1 Axis: Volume

Date Time UTC

d) 选择用户类型 (Creator/Runner/None) ,注意, Creator/Runner 以外的账户无法通过客户端登录。



The screenshot displays a user management interface. On the left is a dark sidebar with navigation options: DEVICES, WORKLOAD, AUDIT LOG, and ADMINISTRATION. Under ADMINISTRATION, the following options are listed: Settings, Users (highlighted with an orange dot), Roles, Licenses, and Migration. The main content area shows a list of user types, each with an unchecked checkbox:

- AAE_Admin
- AAE_Basic
- AAE_Bot Insight Admin
- AAE_Bot Insight Consumer
- AAE_Bot Insight Expert
- AAE_BotFarm Admin
- AAE_BotFarm Agent

Below the list is a section titled "Allocate a device license to" with a yellow underline. It contains the following text:

Device licenses are only applicable if the u

A device, or Client UI, cannot connect to t

license to a Bot creator license, any sched

At the bottom, there is a configuration panel with two columns. The left column has radio buttons for:


- None
- Bot creator (8 license(s) available)

A red arrow points to the "Bot creator" option. The right column contains:



- Requires a De
- Enable
- This all

8. AAE Client 安装


a) 双击安装文件



b) 重复点击 Next



c) 点击 finish



9. 打开 Client,通常选择 User Credentials,利用已创建的 Creator 账户 login。

Client Login

AUTOMATION ANYWHERE
Go be great.

Login to Control Room

Control Room:

e.g https://<hostname>:<port>
Note: Please contact your control room admin in case you need any help.

Authentication:

Windows Single Sign-On User Credentials

Username:

Password:

Login

[Forgot Password?](#)